RBcf: An VCF API for R.

Pierre Lindenbaum / @yokofakun/ Institut du Thorax . Nantes.

April 24, 2020

1 Abstract

RBcf uses the Htslib C API for parsing VCF and BCF files. This API was written by a regular user of the htsjdk library who doesn't like R.

A list of functions is available at: https://github.com/lindenb/rbcf/blob/master/R/rbcf.R

2 Examples

2.1 Htslib and Rbcf versions

Code:

```
# load the library
library(rbcf)
#print the version of the associated htslib
htslib.version()
#print the version of rbcf
rcbf.version()
```

```
> # load the library
> library(rbcf)
> #print the version of the associated htslib
> htslib.version()
[1] "1.10.2"
> #print the version of rbcf
> rcbf.version()
[1] "0.0-1"
>
```

2.2 Open and close a VCF file

Code:

```
# load rbcf
library(rbcf)
# we don't need the index for this file
fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)
# dispose the vcf reader
bcf.close(fp)</pre>
```

Output:

```
> # load rbcf
> library(rbcf)
> # we don't need the index for this file
> fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)
> # dispose the vcf reader
> bcf.close(fp)
[1] TRUE
```

2.3 Print the INFOs in the VCF header

Code:

```
# load rbcf
library(rbcf)
# we don't need the index for this file
fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)
info <- bcf.infos(fp)
# dispose the vcf reader
bcf.close(fp)
# print the table
info</pre>
```

```
> # load rbcf
> library(rbcf)
> # we don't need the index for this file
> fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)
> info <- bcf.infos(fp)
> # dispose the vcf reader
> bcf.close(fp)
```

```
[1] TRUE
> # print the table
> info
                               ID Number
                                                                            Type
INDEL INDEL
                                                          0
                                                                            Flag
IDV
                           IDV
                                                          1 Integer
IMF
                           IMF
                                                          1
                                                                        Float
DP
                               DP
                                                          1 Integer
VDB
                           VDB
                                                          1
                                                                        Float
RPB
                           RPB
                                                          1
                                                                        Float
MQB
                           MQB
                                                                       Float
                                                          1
BQB
                           BQB
                                                          1
                                                                      Float
MQSB
                        MQSB
                                                          1
                                                                      Float
SGB
                           SGB
                                                          1
                                                                      Float
MQOF
                        MQOF
                                                          1
                                                                       Float
ICB
                           ICB
                                                          1
                                                                       Float
HOB
                           HOB
                                                                        Float
                                                          1
AC
                              AC
                                                          A Integer
AN
                              AN
                                                          1 Integer
DP4
                           DP4
                                                          4 Integer
MQ
                              MQ
                                                          1 Integer
INDEL
                                                                                                                                                                                                           "Indicates_that_the_v
IDV
                                                                                                                                                                                             "Maximum_number_of_reads_
IMF
                                                                                                                                                                                      "Maximum<sub>□</sub>fraction<sub>□</sub>of<sub>□</sub>reads<sub>□</sub>
DP
VDB
                     "Variant_Distance_Bias_for_filtering_splice-site_artefacts_in_RNA-seq_data
RPB
                                                                                                                                   "Mann-Whitney Uutest of Read Position Bias
MQB
                                                                                                                            "Mann-Whitney Uutest of Mapping Quality Bias
BQB
                                                                                                                                      "Mann-Whitney Uutest of Base Quality Bias
MQSB
                                                                                         \verb|"Mann-Whitney|| U_{\sqcup} test_{\sqcup} of_{\sqcup} \verb|Mapping|| Quality_{\sqcup} vs_{\sqcup} Strand_{\sqcup} Bias
SGB
                                                                                                                                                                                                                                                           "Segreg
MQOF
                                                                                                                                                                                                    "Fraction of MQ0 reads to more management of MQ0 reads to more management of the more mana
ICB
                                                                                                                                                    "Inbreeding Coefficient Binomial test
HOB
                                                                                                                                                           "Bias_in_the_number_of_HOMs_number_
AC
                                                                                   "Allele\_count\_in\_genotypes\_for\_each\_ALT\_allele,\_in\_the\_s
                                                                                                                                                                                             "Total_{\sqcup}number_{\sqcup}of_{\sqcup}alleles_{\sqcup}
AN
DP4
                                                    \verb|"Number_lof_lhigh-quality_ref-forward_l,_lref-reverse,_lalt-forward_lan| \\
MQ
                                                                                                                                                                                                                                                                 "Aver
```

2.4 Print the FORMATs in the VCF header

Code:

```
# load rbcf
library(rbcf)
# we don't need the index for this file
fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)
fmts <- bcf.formats(fp)
# dispose the vcf reader
bcf.close(fp)
# print the table
fmts</pre>
```

Output:

```
> # load rbcf
> library(rbcf)
> # we don't need the index for this file
> fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)</pre>
> fmts <- bcf.formats(fp)</pre>
> # dispose the vcf reader
> bcf.close(fp)
[1] TRUE
> # print the table
> fmts
   ID Number
                Type
                                                        Description
PL PL
           G Integer "List⊔of⊔Phred-scaled⊔genotype⊔likelihoods"
           1 String
GT GT
                                                         "Genotype"
```

2.5 Print the FILTERs in the VCF header

```
# load rbcf
library(rbcf)
# we don't need the index for this file
fp <- bcf.open("../tests/data/gnomad.exomes.r2.0.1.sites.vcf",FALSE)
flt <- bcf.filters(fp)
# dispose the vcf reader
bcf.close(fp)
# print the table
flt</pre>
```

```
> # load rbcf
> library(rbcf)
> # we don't need the index for this file
> fp <- bcf.open("../tests/data/gnomad.exomes.r2.0.1.sites.vcf",FALSE)</pre>
> flt <- bcf.filters(fp)</pre>
> # dispose the vcf reader
> bcf.close(fp)
[1] TRUE
> # print the table
> flt
                                ID
PASS
                              PASS
AC0
                               ACO
InbreedingCoeff InbreedingCoeff
LCR
                               LCR
RF
                                RF
SEGDUP
                           SEGDUP
PASS
ACO
                 "Allele_Count_is_zero_(i.e._no_high-confidence_genotype_(GQ_>=_2
InbreedingCoeff
LCR
                                                          "Failed_{\sqcup}random_{\sqcup}forests_{\sqcup}filte
RF
SEGDUP
```

2.6 Print the Samples in the VCF header

The samples are defined in the '#CHROM' line of the VCF Code:

```
# load rbcf
library(rbcf)
# we don't need the index for this file
fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)
# print the number of samples
bcf.nsamples(fp)
# get the name for the 1st sample
bcf.sample.at(fp,1)
# get the 1-based index for the samples
bcf.sample2index(fp,c("S1","S2","S3","missing"))</pre>
```

```
# get all the samples
bcf.samples(fp)
# dispose the vcf reader
bcf.close(fp)
```

```
> # load rbcf
> library(rbcf)
> # we don't need the index for this file
> fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)</pre>
> # print the number of samples
> bcf.nsamples(fp)
[1] 5
> # get the name for the 1st sample
> bcf.sample.at(fp,1)
[1] "S1"
> # get the 1-based index for the samples
> bcf.sample2index(fp,c("S1","S2","S3","missing"))
    S1
            S2 S3 missing
     1
             2
                     3
                              0
> # get all the samples
> bcf.samples(fp)
[1] "S1" "S2" "S3" "S4" "S5"
> # dispose the vcf reader
> bcf.close(fp)
[1] TRUE
```

2.7 Print the Dictionary in the VCF header

```
# load rbcf
library(rbcf)
# we don't need the index for this file
fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)
dict <- bcf.dictionary(fp)
# dispose the vcf reader
bcf.close(fp)
# print the table
dict</pre>
```

```
> # load rbcf
> library(rbcf)
> # we don't need the index for this file
> fp <- bcf.open("../tests/data/rotavirus_rf.01.vcf",FALSE)</pre>
> dict <- bcf.dictionary(fp)</pre>
> # dispose the vcf reader
> bcf.close(fp)
[1] TRUE
> # print the table
> dict
     chrom size
RF01 RF01 3302
RF02 RF02 2687
RF03 RF03 2592
RF04 RF04 2362
RF05 RF05 1579
RF06 RF06 1356
RF07 RF07 1074
RF08 RF08 1059
RF09 RF09 1062
RF10 RF10 751
RF11 RF11 666
```

2.8 Print the Indexed Chromosomes

Code:

```
# load rbcf
library(rbcf)
# Open the indexed VCF
fp <- bcf.open("../tests/data/rotavirus_rf.02.vcf.gz")
# get the indexed contigs
contigs <- bcf.contigs(fp)
# dispose the vcf reader
bcf.close(fp)
# print the table
contigs</pre>
```

```
> # load rbcf
> library(rbcf)
> # Open the indexed VCF
> fp <- bcf.open("../tests/data/rotavirus_rf.02.vcf.gz")
> # get the indexed contigs
> contigs <- bcf.contigs(fp)
> # dispose the vcf reader
> bcf.close(fp)
[1] TRUE
> # print the table
> contigs
[1] "RF01" "RF02" "RF03" "RF04" "RF05" "RF06" "RF07" "RF08" "RF09" "RF10"
[11] "RF11"
>
```

2.9 Scanning the variants

```
# load rbcf
library(rbcf)
# create a function counting variants in a VCF
count.variants<-function(filename) {</pre>
        # we don't need the index for this file
        fp <- bcf.open(filename,FALSE)</pre>
        # number of variants
        n<-0
        # loop while we can read a variant
        while(!is.null(vc<-bcf.next(fp))) {</pre>
                # increment the count
                n<-n+1
        # dispose the vcf reader
        bcf.close(fp)
        # return the number of variant
        n
# filenames
vcfs<-c(
```

```
"../tests/data/gnomad.exomes.r2.0.1.sites.vcf",
    "../tests/data/rotavirus_rf.01.vcf",
    "../tests/data/rotavirus_rf.02.vcf.gz",
    "../tests/data/rotavirus_rf.03.vcf.gz",
    "../tests/data/rotavirus_rf.04.bcf"
    )
# print the number of variants for each vcf
for(f in vcfs) {
    cat(paste(f,"\",count.variants(f),"\n"))
    }
```

```
> # load rbcf
> library(rbcf)
> # create a function counting variants in a VCF
> count.variants<-function(filename) {</pre>
        # we don't need the index for this file
        fp <- bcf.open(filename,FALSE)</pre>
        # number of variants
        n<-0
        # loop while we can read a variant
        while(!is.null(vc<-bcf.next(fp))) {</pre>
                # increment the count
                n<-n+1
        }
        # dispose the vcf reader
        bcf.close(fp)
        # return the number of variant
        n
+ }
> # filenames
> vcfs<-c(</pre>
        "../tests/data/gnomad.exomes.r2.0.1.sites.vcf",
        "../tests/data/rotavirus_rf.01.vcf",
        "../tests/data/rotavirus_rf.02.vcf.gz",
        "../tests/data/rotavirus_rf.03.vcf.gz",
        "../tests/data/rotavirus_rf.04.bcf"
> # print the number of variants for each vcf
```

```
> for(f in vcfs) {
+     cat(paste(f,"u",count.variants(f),"\n"))
+     }
../tests/data/gnomad.exomes.r2.0.1.sites.vcf 50
../tests/data/rotavirus_rf.01.vcf 45
../tests/data/rotavirus_rf.02.vcf.gz 45
../tests/data/rotavirus_rf.03.vcf.gz 45
../tests/data/rotavirus_rf.04.bcf 45
>
```

2.10 Scanning the variants

```
# load rbcf
library(rbcf)
# create a function counting variants in a VCF
count.variants<-function(filename,predicate) {</pre>
        # we don't need the index for this file
        fp <- bcf.open(filename,FALSE)</pre>
        # number of variants
        n<-0
        # loop while we can read a variant
        while(!is.null(vc<-bcf.next(fp))) {</pre>
                # test the variant
                if(predicate(vc)) {
                         # increment the count
                         n<-n+1
                         }
        }
        # dispose the vcf reader
        bcf.close(fp)
        # return the number of variant
# A vcf
filename <- "../tests/data/gnomad.exomes.r2.0.1.sites.vcf"
# filters
filters<-list(
```

```
list("desc"="accept_all","predicate"=function(ctx) {TRUE} ),
list("desc"="accept_none","predicate"=function(ctx) {FALSE} ),
list("desc"="CHROM_is_'1'","predicate"=function(ctx) { variant.contig(ct
list("desc"="POS_is_even","predicate"=function(ctx) { (variant.pos(ctx)%
list("desc"="PASS_filter","predicate"=function(ctx) {!variant.is.filtere
list("desc"="FILTER_contains_SEGDUP","predicate"=function(ctx) {variant.
list("desc"="SNP","predicate"=function(ctx) {variant.is.snp(ctx)} ),
list("desc"="not_diallelic","predicate"=function(ctx) {variant.nalleles(
list("desc"="REF_is_'A'","predicate"=function(ctx) {variant.reference(ct
list("desc"="REF_is_'A'","predicate"=function(ctx) {"A" %in% variant.al
)

# count the variant for each filter
for(flt in filters) {
    cat(paste(flt[["desc"]],"_",count.variants(filename,flt[["predicate"]]),
}
```

```
> # load rbcf
> library(rbcf)
> # create a function counting variants in a VCF
> count.variants<-function(filename,predicate) {</pre>
        # we don't need the index for this file
        fp <- bcf.open(filename,FALSE)</pre>
        # number of variants
        n<-0
        # loop while we can read a variant
        while(!is.null(vc<-bcf.next(fp))) {</pre>
                 # test the variant
                if(predicate(vc)) {
                         # increment the count
                         n < -n + 1
                         }
        }
        # dispose the vcf reader
        bcf.close(fp)
        # return the number of variant
```

```
> filename <- "../tests/data/gnomad.exomes.r2.0.1.sites.vcf"</pre>
> # filters
> filters<-list(</pre>
        list("desc"="accept_all", "predicate"=function(ctx) {TRUE} ),
        list("desc"="accept_none", "predicate"=function(ctx) {FALSE} ),
        list("desc"="CHROM_is_'1', "predicate"=function(ctx) { variant.contig(ct
        list("desc"="POS<sub>□</sub>is<sub>□</sub>even", "predicate"=function(ctx) { (variant.pos(ctx)%
        list("desc"="PASS_filter", "predicate"=function(ctx) {!variant.is.filtere
        list("desc"="FILTER_contains_SEGDUP", "predicate"=function(ctx) {variant.
        list("desc"="SNP", "predicate"=function(ctx) {variant.is.snp(ctx)} ),
        list("desc"="not_diallelic", "predicate"=function(ctx) {variant.nalleles(
        list("desc"="REF<sub>□</sub>is<sub>□</sub>'A'", "predicate"=function(ctx) {variant.reference(ct
        list("desc"="REF<sub>□</sub>is<sub>□</sub>'A'", "predicate"=function(ctx) {"A" %in% variant.al
        )
> # count the variant for each filter
> for(flt in filters) {
        cat(paste(flt[["desc"]],"\",count.variants(filename,flt[["predicate"]]),
        }
accept all
accept none
CHROM is '1'
              50
POS is even
               24
PASS filter
               48
FILTER contains SEGDUP
SNP
      47
not diallelic
REF is 'A'
REF is 'A'
             27
```